

Setting up Accesses

Purpose of this How-To

This How-To informs you how to set up the required accesses to the DENIC registration system.

Terms Explained in Brief

DENIC Business Services (DBS)

DBS is your contact for all matters relating to membership and registrar support.

Telephone: +49 69 27 235 290

Email: dbs@denic.de

Environment

The registration system is available to the members in two different environments, with different features. In addition to the Live environment, there is also a test environment.

Technical Onboarding

A new DENIC member must provide details for technical integration (**technical onboarding**). These include information that is necessary for preparing the initial login at the Registrar Administration Interface (RAI).

Registrar Administration Interface (RAI)

Members manage their registration accounts in the **Registrar Administration Interface** web app, in short **RAI**. The RAI is also used to set up the access to the DENIC registration system.

Registration Account

A **registration account** is necessary to register domains with DENIC. Your membership includes one registration account, the primary or basic registration account.

General Request

General Request is a special handle in your registration account.

GeneralRequestUriTemplate

The general request includes the **GeneralRequestUriTemplate** contact information as URL or mailto link for general requests to the registrar or the domain holder about a domain. The contact information is output publicly via web-whois.

Realtime Registry Interface (RRI)

The DENIC registration system works with the **Realtime Registry Interface (RRI)** protocol, via which requests are sent to the registration system.

RRI-Login

Your requests can only be accepted if you authenticate yourself by entering your access data in the DENIC registration system (RRI). To do so, set up an RRI login via the RAI.


Two-factor Authentication

With a two-factor authentication you log on to DENIC at the RAI access point. The first factor is the password of your access and the second factor is a time-limited one-time password (TOTP).

Carrying Out the Technical Onboarding

1 Log in to the member section on the DENIC website.

Press the button [**To Member Section**] on our website to enter your access data.



2 Complete the form.

For technical onboarding, a form with three tabs is used.

Tab 1: Information

On the first tab, enter e-mail addresses for mailing lists and messages that are sent by the registration system. Moreover, you can request authorisation for using the **Test environment**.

Tab 2: RAI Access

In addition to a user name and a password, (tool for generating a **password hash** under: **Hash Generator**), a time-limited one-time password (TOTP) is required for access to the RAI.

Note

In the section **Set up two-factor authentication**, you will learn how you can set up the method for generating time-limited one-time passwords (TOTP) yourself.

For your first login to the RAI, DBS will create a one-time password for you. For this purpose, make an appointment with DBS by entering a **phone number** and a **call-back time** on the tab.

With an **RAI INFO mail**, you will be informed about any changes that have been made to your registration account via the RAI.

Tab 3: Master Key

The **master key** is a PGP key. Every member needs at least one **master key** to be able to send signed e-mails to DBS in order to request or terminate the setting up of additional registration accounts, quotas and additional accesses to the RAI and the member website. Moreover, changes to RAI INFO mails may be requested. General e-mail communication with DENIC can also be signed with the **master key**.

Length of the Key	
minimum 2048 Bit	
Key Types	
DH/DSS	RSA
DSA	DSA and ElGamal
Algorithms	
RIPEMD160withRSA	RIPEMD160withECDSA
RIPEMD256withRSA	SHA256withDSA
SHA256withECDSA	SHA384withDSA
SHA384withECDSA	SHA512withDSA
SHA512withECDSA	SHA256withRSA
SHA384withRSA	SHA512withRSA

Set up two-factor authentication

1 Install an app for your two-factor authentication.

For setting up a 2FA app, this quick guide exemplarily describes how to install the Google Authenticator for Android devices.

If you do not yet use any application for a two-factor authentication, you can download the Google Authenticator for your device with the QR codes below

Google Authenticator



Android



iOS

* QR Code® is a registered trademark of the Denso Wave Incorporated.

2 Enter the access data for the RAI from the technical onboarding.

Note

DENIC Business Services (DBS) has already sent you an e-mail to confirm the creation of the user name and the password defined on the technical onboarding page. At the agreed call-back time, DBS has told you the one-time password for your first login.

In your computer's web browser, open the RAI access site: **RAI-Live**.

Enter your user name, your password and the one-time password.

Note

For all further logins to the RAI, please set up a two-factor authentication (2FA) as described in the following steps.

3 Start the Google Authenticator.


Start the app and read the introductory information.

4 Enable two-factor authentication in Google Authenticator by scanning a QR code.

In the RAI, click the orange button.

ROLL OUT NEW SOFTWARE TOKEN (TOTP)

You will see a QR code on your screen. In the app, tap on the menu item **Scan barcode**. Use your mobile device to scan the QR code.

-  **Your RAI access has been set up now. Start the Google Authenticator whenever you log in to the RAI and enter your user name, your password and the six-digit code (time-based one-time password).**

Editing the Registration Account

1 Select a registration account and complete the mandatory fields.

Select a registration account and click on **Edit** on the page that follows. In new registration accounts, you will find some fields already completed with **dbbs@denic.de**. This has been entered by DBS as a placeholder. Replace these placeholders with your own data and complete the mandatory fields (see table). Save your changes.

Note

The information for your registration account is divided into several sections. Your member and registrar information is shown at the top, followed by your member address and contact details and the setup of the RRI login. The last two blocks are for .de- and ENUM domain information.

To be able to take part in the registration system for .de domains, complete the mandatory fields in the .de domain block (see list below) and carry out the steps described in the **Setting Up Your RRI Login** section.

List of Mandatory Fields

Field	Description	Example
Phone	General phone number	+49 69 27 235 290
Fax	General fax number	+49 69 27 235 238
E-mail	General e-mail address	dbs@denic.de
E-mail hostmaster list	E-mail address for hostmaster-I mailing list	dbs@denic.de
E-Mail tech-announce list	E-mail address for tech-announce-I mailing list	dbs@denic.de
Url	Output of the URL in response to queries by the registration account	https://www.denic.de
MsgFeed	Message feed setting (mail or rri)	rri
GeneralRequest	Handle for general requests	DENIC-99990-BSP
GeneralRequestUriTemplate	Hyperlink or mailto link	mailto:info@denic.de
EmailTo	E-mail address to which the registration system sends e-mails	dbs@denic.de
EmailChprovIn	E-mail address for CHPROVs started by the provider itself	dbs@denic.de
EmailChprovOut	E-mail address for CHPROVs to be acknowledged	dbs@denic.de

Note

The fields „E-mail hostmaster list“, „E-mail tech-announce list“ and „EmailTo“ are already filled with information from the technical onboarding.

Setting Up Your RRI Login

1 Set up an RRI login in the RAI.

Click on the plus symbol to the left of **RRI Login**.



The screenshot shows a web form for setting up an RRI login. It consists of two rows. The first row is labeled 'RRI Login:' and contains a text input field, a dropdown menu currently showing '.de', and a small downward arrow icon. The second row is labeled 'RRI Login Pw:' and contains a text input field and an orange 'ADD' button.

Complete the **RRI Login** field with a handle. In the dropdown list, select whether the RRI login is for either .de or ENUM or for both.

Enter the password in form of an MD5 hash in the field **RRI Login Pw**.

Note

On the DENIC website, we provide a **Hash Generator** for calculating an MD5 hash.

2 Set up the General Request and the GeneralRequestUriTemplate.

If the fields **GeneralRequest** and **GeneralRequestUriTemplate** are empty, you have to fill in these fields.

Enter a handle in the GeneralRequest field and a hyperlink or a mailto link in the field GeneralRequestUriTemplate.

Example of hyperlink

`https://www.denic.de`

Example of mailto

`mailto:info@denic.de`

Note

You can also update existing General Requests here. For GeneralRequestUriTemplate, you may also enter a URI template with variables.

For more detailed information, please consult the documentation **DENIC-22: RAI - Registrar Administration Interface**.


Further Information

Documentation DENIC-22

You find a detailed description of the RAI in the members' section in the technical documentation DENIC-22.

DENIC-22: RAI - Registrar Administration Interface





If you have any
further questions,
do not hesitate to
contact DBS.

+49 69 27 235 290

dbs@denic.de

